

Cisco – Host and Subnet Quantities

Table of Contents

| | |
|--|----------|
| <u>Host and Subnet Quantities</u> | 1 |
| <u>Introduction</u> | 1 |
| <u>Before You Begin</u> | 1 |
| <u>Conventions</u> | 1 |
| <u>Prerequisites</u> | 1 |
| <u>Components Used</u> | 1 |
| <u>Classes</u> | 1 |
| <u>Subnetting and Tables</u> | 2 |
| <u>Class A Host/Subnet Table</u> | 2 |
| <u>Class B Host/Subnet Table</u> | 3 |
| <u>Class C Host/Subnet Table</u> | 3 |
| <u>Subnetting Example</u> | 3 |
| <u>Related Information</u> | 4 |

Host and Subnet Quantities

Introduction

Before You Begin

Conventions

Prerequisites

Components Used

Classes

Subnetting and Tables

Class A Host/Subnet Table

Class B Host/Subnet Table

Class C Host/Subnet Table

Subnetting Example

Related Information

Introduction

An IP address is 32 bits long and made up of two components, a network portion and a host portion. The network address is used to identify the network and is common to all the devices attached to the network. The host (or node) address is used to identify a particular device attached to the network. The IP address is generally represented using the dotted–decimal notation, where 32 bits are divided into four octets. Each of the octets can be represented in a decimal format, separated by decimal points. For more information on IP addressing, see *IP Addressing and Subnetting for New Users*.

Before You Begin

Conventions

For more information on document conventions, see the *Cisco Technical Tips Conventions*.

Prerequisites

There are no specific prerequisites for this document.

Components Used

This document is not restricted to specific software and hardware versions.

Classes

The following are the classes of IP addresses.

- **Class A** – The first octet denotes the network address, and the last three octets are the host portion. Any IP address whose first octet is between 1 and 126 is a Class A address. Note that 0 is reserved as a part of the default address, and 127 is reserved for internal loopback testing.
- **Class B** – The first two octets denote the network address, and the last two octets are the host portion. Any address whose first octet is in the range 128 through 191 is a Class B address.
- **Class C** – The first three octets denote the network address, and the last octet is the host portion. The first octet range of 192 through 223 is a Class C address.

- Class D addresses are for multicast. Multicast IP addresses have their first octets in the range 224 through 239.
- Class E addresses are reserved for experimental usage and includes the range of addresses with a first octet from 240 to 255.

Subnetting and Tables

Subnetting is the concept of dividing the network into smaller portions called subnets. This is done by borrowing bits from the host portion of the IP address, enabling more efficient use of the network address. A subnet mask defines which portion of the address is used to identify the network and which denotes the hosts.

The following tables show all possible ways a major network can be subnetted, and, in each case, how many effective subnets and hosts are possible.

There are three tables, one for each class of addresses.

- The first column shows how many bits are borrowed from the host portion of the address for subnetting.
- The second column shows the resulting subnet mask in dotted decimal format.
- The third column shows how many subnets are possible.
- The fourth column shows how many valid hosts are possible on each of these subnets.
- The fifth column shows the number of subnet mask bits.

Class A Host/Subnet Table

| Class A Number of Bits Borrowed from Host Portion | Subnet Mask | Effective Subnets | Number of Hosts/Subnet | Number of Subnet Mask Bits |
|--|-----------------|----------------------|---------------------------|-------------------------------|
| 2 | 255.192.0.0 | 4 | 4194302 | /10 |
| 3 | 255.224.0.0 | 8 | 2097150 | /11 |
| 4 | 255.240.0.0 | 16 | 1048574 | /12 |
| 5 | 255.248.0.0 | 32 | 524286 | /13 |
| 6 | 255.252.0.0 | 64 | 262142 | /14 |
| 7 | 255.254.0.0 | 128 | 131070 | /15 |
| 8 | 255.255.0.0 | 256 | 65534 | /16 |
| 9 | 255.255.128.0 | 512 | 32766 | /17 |
| 10 | 255.255.192.0 | 1024 | 16382 | /18 |
| 11 | 255.255.224.0 | 2048 | 8190 | /19 |
| 12 | 255.255.240.0 | 4096 | 4094 | /20 |
| 13 | 255.255.248.0 | 8192 | 2046 | /21 |
| 14 | 255.255.252.0 | 16384 | 1022 | /22 |
| 15 | 255.255.254.0 | 32768 | 510 | /23 |
| 16 | 255.255.255.0 | 65536 | 254 | /24 |
| 17 | 255.255.255.128 | 131072 | 126 | /25 |
| 18 | 255.255.255.192 | 262144 | 62 | /26 |
| 19 | 255.255.255.224 | 524288 | 30 | /27 |
| 20 | 255.255.255.240 | 1048576 | 14 | /28 |
| 21 | 255.255.255.248 | 2097152 | 6 | /29 |
| 22 | 255.255.255.252 | 4194304 | 2 | /30 |

Class B Host/Subnet Table

| Class B Bits | Subnet Mask | Effective Subnets | Effective Hosts | Number of Subnet Mask Bits |
|-----------------|-----------------|----------------------|--------------------|-------------------------------|
| 2 | 255.255.192.0 | 4 | 16382 | /18 |
| 3 | 255.255.224.0 | 8 | 8190 | /19 |
| 4 | 255.255.240.0 | 16 | 4094 | /20 |
| 5 | 255.255.248.0 | 32 | 2046 | /21 |
| 6 | 255.255.252.0 | 64 | 1022 | /22 |
| 7 | 255.255.254.0 | 128 | 510 | /23 |
| 8 | 255.255.255.0 | 256 | 254 | /24 |
| 9 | 255.255.255.128 | 512 | 126 | /25 |
| 10 | 255.255.255.192 | 1024 | 62 | /26 |
| 11 | 255.255.255.224 | 2048 | 30 | /27 |
| 12 | 255.255.255.240 | 4096 | 14 | /28 |
| 13 | 255.255.255.248 | 8192 | 6 | /29 |
| 14 | 255.255.255.252 | 16384 | 2 | /30 |

Class C Host/Subnet Table

| Class C Bits | Subnet Mask | Effective Subnets | Effective Hosts | Number of Subnet Mask Bits |
|-----------------|-----------------|----------------------|--------------------|-------------------------------|
| 2 | 255.255.255.192 | 4 | 62 | /26 |
| 3 | 255.255.255.224 | 8 | 30 | /27 |
| 4 | 255.255.255.240 | 16 | 14 | /28 |
| 5 | 255.255.255.248 | 32 | 6 | /29 |
| 6 | 255.255.255.252 | 64 | 2 | /30 |

Subnetting Example

The first entry in the Class A table (/10 subnet mask) borrows two bits (the leftmost bits) from the host portion of the network for subnetting, then with two bits you have four (2²) combinations, 00, 01, 10, and 11. Each of these will represent a subnet.

| Binary Notation | Decimal Notation |
|---|---------------------|
| xxxx xxxx. 0000 0000.0000 0000.0000 0000/10 | -----> X.0.0.0/10 |
| xxxx xxxx. 0100 0000.0000 0000.0000 0000/10 | -----> X.64.0.0/10 |
| xxxx xxxx. 1000 0000.0000 0000.0000 0000/10 | -----> X.128.0.0/10 |
| xxxx xxxx. 1100 0000.0000 0000.0000 0000/10 | -----> X.192.0.0/10 |

Out of these four subnets, 00 and 11 are called subnet zero and the all-ones subnet, respectively. Prior to Cisco IOS® Software Release 12.0, the **ip subnet-zero** global configuration command was required to be able to configure subnet zero on an interface. In Cisco IOS 12.0, **ip subnet-zero** is enabled by default. For more information on the all-ones subnet and subnet zero, refer to Subnet Zero and the All-Ones Subnet.

Note: The subnet zero and all-ones subnet are included in the effective number of subnets as shown in the third column.

Since the host portion has now lost two bits, the host portion will have only 22 bits (out of the last three octets). This means the complete Class A network is now divided (or subnetted) into four subnets, and each subnet can have 2²² hosts (4194304). A host portion with all zeros is network number itself, and a host portion with all ones is reserved for broadcast on that subnet, leaving the effective number of hosts to 4194302 (2²² –

2), as shown in the fourth column.

Related Information

- **IP Subnet Calculator**
 - **IP Addressing and Subnetting for New Users**
 - **IP Subnet Calculation and Design Online Documentation**
 - **Internet Protocols**
 - **Configuring IP Access Lists**
 - **Technical Support – Cisco Systems**
-

All contents are Copyright © 1992–2003 Cisco Systems, Inc. All rights reserved. Important Notices and Privacy Statement.